

SedonaCloud - Technical Configuration - New API Endpoints

1.41.4.1

12/28/2023 2:57 pm EST

This new end point is for #26320 SedonaCloud API -- POST API /api/part/PartTransferWarehouse not available

POST PartTransferWarehouse

This creates the warehouse transfer for the specified part.

- PartCode - Required. Specifies the part being transferred.
- FromWarehouseCode - Required. Specifies the warehouse from which the part will be transferred.
- ToWarehouseCode - Required. Specifies the warehouse to which the part will be transferred.
- Quantity - Required and must be greater than zero.
- TransferDate - Optional. If not supplied or a date prior to 2000-01-01 is supplied, the time at which the request is made will be used.
- Reference - Optional. Populates the Reference field of the transfer.
- UserCode - Optional. Populates the User Code field of the transfer.
- SerialNumber - Optional. Specifies the serial number of the part being transferred.
- LotNumber - Optional. Specifies the lot number of the part being transferred.
- TransferId - Incoming value is ignored. Response contains the TransferId created.
- PrimaryRegisterId - Incoming value is ignored. Response contains the PrimaryRegisterId if GL Register entries are created; otherwise 0. GL Register entries are created when COGS > 0 and the warehouse GL accounts or branches are different.

POST PartTransfers

This retrieves part transfers according the specified search parameters.

- PartCode - Used when filter includes PartCode; otherwise ignored.

- WarehouseCode - Used when filter includes WarehouseCode; otherwise ignored.
- FetchCode - Specifies the type of filtering to apply:
 - 0 = Filter on PartCode and WarehouseCode
 - 1 = Filter on WarehouseCode
 - 2 = Filter on PartCode
 - 3 = No filter