

Firewall /Antivirus Settings For Installer & Updates

04/09/2025 12:04 pm EDT

Firewall:

Allow 1433, and 4992 TCP/UDP from workstations to SQL Instance

Add program exception for SedonaService.exe through the firewall (in C:\Windows\SYSWOW64\)

&

%ProgramFiles%\Microsoft SQL Server\MSSQL16.YOURSQLINSTANCE\MSSQL\Binn\sqlservr.exe or equivalent

Note: SedonaService is required to initiate sessions between the Software and SQL. After the initial client session is started on 4992, the client server connection takes an available port base of 6000 and port range of 250 ports [6001-6250] as listed in the registry HKLM\SOFTWARE\WOW6432Node\Sedona Development Company\Sedona Office Server

Note: SedonaService is required to initiate sessions between the Software and SQL. After the initial client session is started on 4992, the client server connection takes an available port base of 6000 and port range of 250 ports [6001-6250] as listed in in the registry HKLM\SOFTWARE\WOW6432Node\Sedona Development Company\Sedona Office Server

Antivirus and Security Programs:

Whitelist install directory C:\Users\ANYUSER\AppData\Local\Temp\ir_sf_temp_0\irsetup.exe

Files KILLSO.EXE or PSKILL.EXE
